

## 9.8 Professional use of silver nitrate in the photographic sector

1. Title of Exposure Scenario number 9.8: Professional use of silver nitrate in the photographic sector	
List of all use descriptors	SU: 6b PC: 30 ERC: 8c PROC: 1, 2, 3, 4, 5, 8a, 8b, 9, 10, 13, 14, 15, 19, 20, 21
Name of contributing environmental scenario and corresponding ERC	<b>Contributing scenario 1</b> Environmental exposure scenario for the professional use of silver nitrate in the photographic sector ERC 8c (Wide dispersive indoor use resulting in inclusion into or onto a matrix)
Names of contributing occupational scenario and corresponding PROCs	<b>Contributing scenario 2</b> Handling of solutions containing silver nitrate during professional use PROC: 1, 2, 3, 4, 5, 8a, 8b, 9, 10, 13, 15, 19, 20 <b>Contributing scenario 3</b> Handling of silver nitrate crystals during professional use PROC: 1, 2, 3, 4, 5, 8a, 8b, 9, 14, 15, 19, 20, 21
Assessment Method	Environmental modelling was carried out in EUSES 2.1. Occupational exposure was based on the exposure estimation tool MEASE.
2.1 Contributing exposure scenario 1 (environmental exposure scenario 1): Environmental exposure scenario for the professional use of silver nitrate in the photographic sector	
2.1.1 Operational conditions and risk management measures	
ERC	REACH description
ERC 8c	Wide dispersive indoor use resulting in inclusion into or onto a matrix
2.1.2 Control of environmental exposure	
Product characteristics	
<i>Liquid, not biodegradable</i>	
Amounts used	
<i>Maximum site tonnage 0.000635 tpa based on maximal reported site tonnage for the DU sector</i>	
Frequency and duration of use	
<i>Continuous use, 200 days/year based on SPERC factsheet 'Use of intermediates v2.1'</i>	
Monitored Emissions	
<i>No (generic default emissions applied based on SPERCS)</i>	
Annual measured tonnage emitted to air/water	
<i>Not applicable</i>	
Environment factors not influenced by risk management	
<i>Default data for receiving water and for the municipal sewage treatment plant are 18 000 m<sup>3</sup>/d and 2000 m<sup>3</sup>/d, respectively (resulting dilution factor to the receiving water: 10). For marine assessments a default additional tenfold dilution is assumed.</i>	
Technical onsite conditions and measures to reduce or limit discharges, air emissions and releases to soil	
<p><i>Air:</i> No measured emission data. Emissions from SPERC factsheet 'Use of intermediates v2.1'</p> <p><i>Waste water:</i> Wastewater emissions are based on measured data which are considered representative of downstream use. Assumed waste water goes to sewage treatment works in local freshwater assessment. Assumed waste water by-passes sewage treatment works in local marine assessment.</p> <p><i>Soil:</i> There are no direct emissions to soil but it is assumed that sewage sludge is applied to land (which may not be applicable in many cases). Modelled release factors to air 0%, water 40% before STP, soil 0%.</p>	
Conditions and measures related to municipal sewage treatment plant	
<i>EUSES default STP with primary settler with effluent discharge rate 2000m<sup>3</sup>/d, serving 10000 inhabitants. Zero degradation assumed. Partitioning: 80.1% to sludge, 19.9 % to water calculated based on measured partition coefficients. Sludge assumed to be spread to agricultural land.</i>	

**Conditions and measures related to external treatment of waste for disposal**

Hazardous waste from onsite risk management measures and solid or liquid wastes from production, use and cleaning processes should be disposed of separately to hazardous waste incineration plants or hazardous waste landfills as hazardous waste. Releases to the floor, water and soil are to be prevented. If the silver content of the waste is elevated enough, internal or external recovery/recycling might be considered.

Fraction of daily/annual use expected in waste: 0%

Appropriate waste codes: 06 05 02\*, 08 01 11, 08 03 12\*, 09 01 01\*, 09 01 03\*, 09 01 04\*, 09 01 05\*, 09 01 06\*, 09 01 13\*, 10 06 06\*, 10 07 01, 10 07 02, 10 07 03, 10 07 04, 10 07 05, 11 01 09\*, 15 01 10\*, 15 02 02\*, 16 01 18, 16 03 03\*, 16 08 01, 16 11 04

Suitable disposal: Hazardous waste produced during the manufacture and downstream use is sent to a recycler only marginal amounts are sent to a landfill or an incinerator. Waste containing silver is recycled for almost a 100%

A detailed assessment has been performed on modelled and measured data and is reported in the Waste report (ARCHE, 2013)

**Conditions and measures related to external recovery of waste**

Waste generated under the form of sweeps, emission cleaning dusts and off spec material should be recycled into the processing system.

The focus of the silver industry is on the minimisation of waste by optimising the process and by utilizing residues and wastes as far as possible. The residues arising from different stages of the production process are therefore used as raw materials for other processes and an extensive network of metallurgical operators has been established for many years to increase the recovery of metals and eliminate the quantities of waste for disposal.

With regards to the end of life, silver is fully recyclable and the silver content in the end of life material often determines the value of the waste.

**2.2 Contributing exposure scenario 2 (occupational exposure scenario 1): Handling of solutions containing silver nitrate during professional use****2.2.1 Operational conditions and risk management measures**

PROCs	REACH definition	Involved tasks
PROC 1, 2	Use in closed, continuous process with occasional controlled exposure (PROC1 cannot be assessed for professional settings in MEASE, instead PROC2 was assessed as a surrogate)	Processes for which the exposure potential is driven by the level of containment rather than the process itself.
PROC 3	Use in closed batch process (synthesis or formulation)	
PROC 4	Use in batch and other process (synthesis) where opportunity for exposure arises	
PROC 5	Mixing or blending in batch processes for formulation of preparations and articles (multistage and/or significant contact)	Mixing, blending
PROC 8a	Transfer of substance or preparation (charging/discharging) from/to vessels/large containers at dedicated facilities	Handling of substances, shipping, transportation, weighing, packaging and unpacking
PROC 8b	Transfer of substance or preparation (charging/discharging) from/to vessels/large containers at dedicated facilities	Handling of substances, shipping, transportation, weighing, packaging and unpacking
PROC 9	Transfer of substance or preparation into small containers (dedicated filling line, including weighing)	Handling of substances, shipping, transportation, weighing, packaging and unpacking
PROC 10	Roller application or brushing	Low energy spreading
PROC 13	Treatment of articles by dipping and pouring	Immersion operations, acid polishing, anodising
PROC 15	Use as laboratory reagent	Laboratory reagent, sampling for quality assurance
PROC 19	Hand-mixing with intimate contact and only PPE available	Hand-mixing
PROC 20	Heat and pressure transfer fluids in dispersive, professional use but closed systems	Handling of heat and pressure transfer fluids

## 2.2.2 Control of workers exposure

### Product characteristics

According to the MEASE approach, the substance-intrinsic emission potential is one of the main exposure determinants. This is reflected by an assignment of a so-called fugacity class in the MEASE tool. For operations conducted with solid substances at ambient temperature the fugacity is based on the dustiness of that substance. To determine the dustiness of a substance, a dustiness test may be performed. The rotating drum (modified Heubach) method can be used, to reflect potential dustiness during handling of a substance. In hot metal operations, fugacity is temperature based, taking into account the process temperature and the melting point of the substance. As a third group, abrasive tasks are based on the level of abrasion instead of the substance intrinsic emission potential. Although handling of aqueous solutions is usually associated with a very low emission potential, the spraying of aqueous solutions is assumed to be involved with medium emission. Further information can be found in the glossary of the MEASE tool ([www.ebrc.de/mease.html](http://www.ebrc.de/mease.html)).

PROC	Use in preparation	Content in preparation	Physical form	Emission potential
All applicable PROCs	not restricted		aqueous solution	very low

### Amounts used

The actual tonnage handled/used per shift is not explicitly considered to influence the exposure as such for this scenario. Instead, the combination of the scale of operation (industrial vs. professional) and level of containment/automation (as reflected in the PROCs and technical conditions) is the main determinant of the process-intrinsic emission potential.

### Frequency and duration of use/exposure

PROC	Duration of exposure (per shift/day)
All applicable PROCs	480 minutes (not restricted)

### Human factors not influenced by risk management

The shift breathing volume covering all process steps is assumed to be 10 m<sup>3</sup>/shift (8 hours).

### Technical conditions and measures at process level (source) to prevent release

PROC	Level of containment	Level of segregation
PROC 1, 2	closed process	not required
PROC 3	closed process	not required
PROC 20	closed process	not required
All other applicable PROCs	Risk management measures at the process level (e.g. containment or segregation of the emission source) are generally not required in the processes.	

### Technical conditions and measures to control dispersion from source towards the worker

PROC	Level of separation	Localised controls (LC)	Efficiency of LC (according to MEASE)*	Further information
PROC 8b	Separation of workers is generally not required.	local exhaust ventilation	77 %	-
All other applicable PROCs		not required	na	-

\*It has to be assured that localised controls like local exhaust ventilation systems are inspected and maintained at appropriate frequencies to guarantee the functionality and efficiency.

### Organisational measures to prevent /limit releases, dispersion and exposure

General good occupational hygiene practices are required to ensure safe handling of the substance. These include (i) measures to avoid any contamination of private households via the work-home-interface (e.g. shower and change clothes at end of work shift), (ii) good housekeeping practices in the workplace (i.e. regular cleaning with suitable cleaning devices and immediate cleaning in case of splashes and overspill), and (iii) measures to minimise inadvertent ingestion exposure (e.g. no eating and smoking in the workplace). In general, inhalation and ingestion of the substance should be avoided. Certified working clothing and shoes should be worn during work. In addition, the following principles should be followed: (i) ensure good general ventilation in the workplace, and (ii) do not blow dust (including dust remaining from dried splashes) off with compressed air. Regular training of workers in workplace hygiene practice and proper use of personal protective equipment is required.

Conditions and measures related to personal protection, hygiene and health evaluation			
PROC	Specification of respiratory protective equipment (RPE) and assigned protection factor (APF)	Specification of gloves	Further personal protective equipment (PPE)
PROC 4	FFP2 mask APF=10	Since silver nitrate is classified as corrosive to skin, protective gloves according to EN 374 have to be worn at all workplaces unless any contact with the substance can be excluded by the emission potential of silver nitrate resulting from the nature of the process, applied exposure prevention measures and physical appearance of silver nitrate in the specific type of application (e.g. protecting from splashes by containment of emission source). Gloves have to be changed according to manufacturer's information or when damaged, whatever is the earlier.	Due to the eye damaging properties of silver nitrate, direct contact with the eyes is to be avoided including hand to eye transfer after touching contaminated surfaces. Suitable eye protection equipment (e.g. goggles or visors) must be worn, unless contact of the substance with the eye can be excluded. Such exclusion is determined by: (i) the physical appearance of the substance in the specific type of application (e.g. wetting the substance can effectively prevent from the emission of dust), (ii) the emission potential resulting from the nature of the process (e.g. splashes, emission of dust can be excluded in a closed process) and (iii) applied exposure prevention measures (segregation of the emission source or separation of the worker from the emission source). Additionally, face protection, protective clothing and safety shoes are required to be worn as appropriate.
PROC 5			
PROC 8a			
PROC 9			
PROC 10			
PROC 13			
PROC 19	not required		
All other applicable PROCs			

The use of personal protective equipment should always be seen as a last resort after operational conditions and further risk management measures have been improved.

Any RPE as defined above shall only be worn if the following principles are implemented in parallel: The duration of work (compare with "duration of exposure" above) should reflect the additional physiological stress for the worker due to the breathing resistance and mass of the RPE itself, due to the increased thermal stress by enclosing the head. In addition, it shall be considered that the worker's capability of using tools and of communicating are reduced during the wearing of RPE.

For reasons as given above, the worker should therefore be (i) healthy (especially in view of medical problems that may affect the use of RPE), (ii) have suitable facial characteristics reducing leakages between face and mask (in view of scars and facial hair). The recommended devices above which rely on a tight face seal will not provide the required protection unless they fit the contours of the face properly and securely.

The employer and self-employed persons have legal responsibilities for the maintenance and issue of respiratory protective devices and the management of their correct use in the workplace. Therefore, they should define and document a suitable policy for a respiratory protective device programme including training of the workers.

An overview of the APFs of different RPE (according to BS EN 529:2005) can be found in the glossary of MEASE.

### 2.3 Contributing exposure scenario 3 (occupational exposure scenario 2): Handling of silver nitrate crystals during professional use

#### 2.3.1 Operational conditions and risk management measures

PROCs	REACH definition	Involved tasks
PROC 1, 2	Use in closed, continuous process with occasional controlled exposure	Processes for which the exposure potential is driven by the level of containment rather than the process itself.
PROC 3	Use in closed batch process (synthesis or formulation)	
PROC 4	Use in batch and other process (synthesis) where opportunity for exposure arises	
PROC 5	Mixing or blending in batch processes for formulation of preparations and articles (multistage and/or significant contact)	Mixing, blending
PROC 8a	Transfer of substance or preparation (charging/discharging) from/to vessels/large containers at dedicated facilities	Handling of substances, shipping, transportation, weighing, packaging and unpacking
PROC 8b	Transfer of substance or preparation (charging/discharging) from/to vessels/large containers at dedicated facilities	Handling of substances, shipping, transportation, weighing, packaging and unpacking
PROC 9	Transfer of substance or preparation into small containers (dedicated filling line, including weighing)	Handling of substances, shipping, transportation, weighing, packaging and unpacking
PROC 14	Production of preparations or articles by tableting, compression, extrusion, pelletisation	Processing of preparations and/or substances into preparations or articles.
PROC 15	Use as laboratory reagent	Laboratory reagent, sampling for quality assurance
PROC 19	Hand-mixing with intimate contact and only PPE available	Hand-mixing
PROC 20	Heat and pressure transfer fluids in dispersive, professional use but closed systems	Handling of heat and pressure transfer fluids
PROC 21	Low energy manipulation of substances bound in materials and/or articles	Manual cutting, cold rolling or assembly

## 2.3.2 Control of workers exposure

### Product characteristics

According to the MEASE approach, the substance-intrinsic emission potential is one of the main exposure determinants. This is reflected by an assignment of a so-called fugacity class in the MEASE tool. For operations conducted with solid substances at ambient temperature the fugacity is based on the dustiness of that substance. To determine the dustiness of a substance, a dustiness test may be performed. The rotating drum (modified Heubach) method can be used, to reflect potential dustiness during handling of a substance. In hot metal operations, fugacity is temperature based, taking into account the process temperature and the melting point of the substance. As a third group, abrasive tasks are based on the level of abrasion instead of the substance intrinsic emission potential. Although handling of aqueous solutions is usually associated with a very low emission potential, the spraying of aqueous solutions is assumed to be involved with medium emission. Further information can be found in the glossary of the MEASE tool ([www.ebrc.de/mease.html](http://www.ebrc.de/mease.html)).

PROC	Use in preparation	Content in preparation	Physical form*	Emission potential
PROC 20	not restricted		crystals dissolved in water or other solvent ("aqueous solution" used as a surrogate in MEASE)	very low
All other applicable PROCs			crystals	very low

\*For the exposure assessments in MEASE, the physical form "massive object" is used as a surrogate in order to reflect the very low emission potential of silver nitrate crystals unless otherwise stated below. Since the combination of "massive object" and PROC 19 is not possible in MEASE, "aqueous solution" was used in order to reflect a very low emission potential of silver nitrate crystals for this process step.

### Amounts used

The actual tonnage handled/used per shift is not explicitly considered to influence the exposure as such for this scenario. Instead, the combination of the scale of operation (industrial vs. professional) and level of containment/automation (as reflected in the PROCs and technical conditions) is the main determinant of the process-intrinsic emission potential.

### Frequency and duration of use/exposure

PROC	Duration of exposure (per shift/day)
All applicable PROCs	480 minutes (not restricted)

### Human factors not influenced by risk management

The shift breathing volume covering all process steps is assumed to be 10 m<sup>3</sup>/shift (8 hours).

### Technical conditions and measures at process level (source) to prevent release

PROC	Level of containment	Level of segregation
PROC 1, 2	closed process	not required
PROC 3	closed process	not required
PROC 20	closed process	not required
All other applicable PROCs	Risk management measures at the process level (e.g. containment or segregation of the emission source) are generally not required in the processes.	

### Technical conditions and measures to control dispersion from source towards the worker

PROC	Level of separation	Localised controls (LC)	Efficiency of LC (according to MEASE)*	Further information
PROC 8b	Separation of workers is generally not required.	local exhaust ventilation	77 %	-
All other applicable PROCs		not required	na	-

\*It has to be assured that localised controls like local exhaust ventilation systems are inspected and maintained at appropriate frequencies to guarantee the functionality and efficiency.

### Organisational measures to prevent limit releases, dispersion and exposure

General good occupational hygiene practices are required to ensure safe handling of the substance. These include (i) measures to avoid any contamination of private households via the work-home-interface (e.g. shower and change clothes at end of work shift), (ii) good housekeeping practices in the workplace (i.e. regular cleaning with suitable cleaning devices and immediate cleaning in case of splashes and overspill), and (iii) measures to minimise inadvertent ingestion exposure (e.g. no eating and smoking in the workplace). In general, inhalation and ingestion of the substance should be avoided. Certified working clothing and shoes should be worn during work. In addition, the following principles should be followed: (i) ensure good general ventilation in the workplace, and (ii) do not blow dust (including dust remaining from dried splashes) off with compressed air. Regular training of workers in workplace hygiene practice and proper use of personal protective equipment is required.

Conditions and measures related to personal protection, hygiene and health evaluation						
PROC	Specification of respiratory protective equipment (RPE) and assigned protection factor (APF)	Specification of gloves	Further personal protective equipment (PPE)			
PROC 4	FFP2 mask APF=10	Since silver nitrate is classified as corrosive to skin, protective gloves according to EN 374 have to be worn at all workplaces unless any contact with the substance can be excluded by the emission potential of silver nitrate resulting from the nature of the process, applied exposure prevention measures and physical appearance of silver nitrate in the specific type of application (e.g. protecting from splashes by containment of emission source). Gloves have to be changed according to manufacturer's information or when damaged, whatever is the earlier.	Due to the eye damaging properties of silver nitrate, direct contact with the eyes is to be avoided including hand to eye transfer after touching contaminated surfaces. Suitable eye protection equipment (e.g. goggles or visors) must be worn, unless contact of the substance with the eye can be excluded. Such exclusion is determined by: (i) the physical appearance of the substance in the specific type of application (e.g. wetting the substance can effectively prevent from the emission of dust), (ii) the emission potential resulting from the nature of the process (e.g. splashes, emission of dust can be excluded in a closed process) and (iii) applied exposure prevention measures (segregation of the emission source or separation of the worker from the emission source). Additionally, face protection, protective clothing and safety shoes are required to be worn as appropriate.			
PROC 5						
PROC 8a						
PROC 9						
PROC 14						
PROC 19						
PROC 21	not required					
All other applicable PROCs						
<p>The use of personal protective equipment should always be seen as a last resort after operational conditions and further risk management measures have been improved.</p> <p>Any RPE as defined above shall only be worn if the following principles are implemented in parallel: The duration of work (compare with "duration of exposure" above) should reflect the additional physiological stress for the worker due to the breathing resistance and mass of the RPE itself, due to the increased thermal stress by enclosing the head. In addition, it shall be considered that the worker's capability of using tools and of communicating are reduced during the wearing of RPE.</p> <p>For reasons as given above, the worker should therefore be (i) healthy (especially in view of medical problems that may affect the use of RPE), (ii) have suitable facial characteristics reducing leakages between face and mask (in view of scars and facial hair). The recommended devices above which rely on a tight face seal will not provide the required protection unless they fit the contours of the face properly and securely.</p> <p>The employer and self-employed persons have legal responsibilities for the maintenance and issue of respiratory protective devices and the management of their correct use in the workplace. Therefore, they should define and document a suitable policy for a respiratory protective device programme including training of the workers.</p> <p>An overview of the APFs of different RPE (according to BS EN 529:2005) can be found in the glossary of MEASE.</p>						
<b>3. Exposure estimation and reference to its source</b>						
<b>3.1 Environmental emissions (Contributing scenario 1)</b>						
Environmental modelling was carried out in EUSES 2.1						
Local PEC (*) used to calculate the maximal tonnage for safe use under default conditions						
Air mg/m <sup>3</sup> (RCR)	Fresh water mg/L (RCR)	Marine water mg/L (RCR)	Sediment freshwater mg/kg wwt (RCR)	Sediment marine water mg/kg wwt (RCR)	Soil mg/kg wwt (RCR)	STP mg/L (RCR)
8.53E-08 (NA)	6.39E-06 (0.16)*	2.07E-06 (2.41E-03)	0.265 (2.78E-03)	0.0859 (9.02E-04)	0.0769 (0.062)	1.26E-05 (5.05E-04)

**3.2a Occupational exposure (Contributing scenario 2), Handling of solutions containing silver nitrate during professional use - Exposure estimation, reference to its source and quantitative risk characterisation**

The exposure estimation tool MEASE (version 1.02.01) was used for the assessment of occupational exposure. The risk characterisation ratio (RCR) is the quotient of the exposure estimate and the DNEL (derived no-effect level) and has to be below 1 to demonstrate a safe use. For inhalation exposure, the RCR is based on the DNEL (long-term, systemic) for silver nitrate of 0.016 mg/m<sup>3</sup> (corresponding to 0.01 mg Ag/m<sup>3</sup>).

PROC	Method used for inhalation exposure assessment (refer to introduction)	Inhalation exposure estimate (RCR)
PROC 1, 2	MEASE	0.001 mg/m <sup>3</sup> (0.06)
PROC 3	MEASE	0.01 mg/m <sup>3</sup> (0.63)
PROC 4	MEASE	0.01 mg/m <sup>3</sup> (0.63)
PROC 5	MEASE	0.01 mg/m <sup>3</sup> (0.63)
PROC 8a	MEASE	0.005 mg/m <sup>3</sup> (0.31)
PROC 8b	MEASE	0.012 mg/m <sup>3</sup> (0.72)
PROC 9	MEASE	0.005 mg/m <sup>3</sup> (0.31)
PROC 10	MEASE	0.005 mg/m <sup>3</sup> (0.31)
PROC 13	MEASE	0.005 mg/m <sup>3</sup> (0.31)
PROC 15	MEASE	0.01 mg/m <sup>3</sup> (0.63)
PROC 19	MEASE	0.005 mg/m <sup>3</sup> (0.31)
PROC 20	MEASE	0.001 mg/m <sup>3</sup> (0.06)

**3.2b Occupational exposure (Contributing scenario 2), Handling of solutions containing silver nitrate during professional use - Qualitative risk characterisation**

In the table on the scope of risk characterisation above, human health effects were identified for which a qualitative risk characterisation has to be conducted. For all identified routes and types of effects, the qualitative risk characterisation can be found in the table below.

Route of exposure and type of effects	Prescribed Risk Management Measures and Operational Conditions	Risk characterisation
Dermal, local effect / long-term	Due to the potential of the substance to cause local effects, appropriate personal protective equipment is prescribed to be worn unless any contact with the substance can be excluded by the emission potential of the substance resulting from the nature of the process, applied exposure prevention measures and physical appearance of the substance in the specific type of application (e.g. protecting from splashes by containment of emission source).	Although the quantitative risk characterisation, already demonstrated that the prescribed operational conditions and risk management measures effectively control exposure well below the respective DNELs, it cannot be excluded that residual exposure concentrations may lead to local effects. As a precautionary measure, it is therefore prescribed to use personal protective equipment in situations in which such residual exposure concentrations cannot be excluded. The risk of local effects is therefore adequately controlled.
Dermal, local effect / acute		
Eyes, local effect		

**3.3a Occupational exposure (Contributing scenario 3), Handling of silver nitrate crystals during professional use - Exposure estimation, reference to its source and quantitative risk characterisation**

The exposure estimation tool MEASE (version 1.02.01) was used for the assessment of occupational exposure. The risk characterisation ratio (RCR) is the quotient of the exposure estimate and the DNEL (derived no-effect level) and has to be below 1 to demonstrate a safe use. For inhalation exposure, the RCR is based on the DNEL (long-term, systemic) for silver nitrate of 0.016 mg/m<sup>3</sup> (corresponding to 0.01 mg Ag/m<sup>3</sup>).

PROC	Method used for inhalation exposure assessment (refer to introduction)	Inhalation exposure estimate (RCR)
PROC 1, 2	MEASE	0.001 mg/m <sup>3</sup> (0.06)
PROC 3	MEASE	0.01 mg/m <sup>3</sup> (0.63)
PROC 4	MEASE	0.01 mg/m <sup>3</sup> (0.63)
PROC 5	MEASE	0.01 mg/m <sup>3</sup> (0.63)
PROC 8a	MEASE	0.005 mg/m <sup>3</sup> (0.31)
PROC 8b	MEASE	0.012 mg/m <sup>3</sup> (0.72)
PROC 9	MEASE	0.005 mg/m <sup>3</sup> (0.31)
PROC 14	MEASE	0.01 mg/m <sup>3</sup> (0.63)
PROC 15	MEASE	0.01 mg/m <sup>3</sup> (0.63)
PROC 19	MEASE	0.005 mg/m <sup>3</sup> (0.31)
PROC 20	MEASE	0.001 mg/m <sup>3</sup> (0.06)
PROC 21	MEASE	0.005 mg/m <sup>3</sup> (0.31)

**3.3b Occupational exposure (Contributing scenario 3), Handling of silver nitrate crystals during professional use - Qualitative risk characterisation**

In the table on the scope of risk characterisation above, human health effects were identified for which a qualitative risk characterisation has to be conducted. For all identified routes and types of effects, the qualitative risk characterisation can be found in the table below.

Route of exposure and type of effects	Prescribed Risk Management Measures and Operational Conditions	Risk characterisation
Dermal, local effect / long-term	Due to the potential of the substance to cause local effects, appropriate personal protective equipment is prescribed to be worn unless any contact with the substance can be excluded by the emission potential of the substance resulting from the nature of the process, applied exposure prevention measures and physical appearance of the substance in the specific type of application (e.g. protecting from splashes by containment of emission source).	Although the quantitative risk characterisation, already demonstrated that the prescribed operational conditions and risk management measures effectively control exposure well below the respective DNELs, it cannot be excluded that residual exposure concentrations may lead to local effects. As a precautionary measure, it is therefore prescribed to use personal protective equipment in situations in which such residual exposure concentrations cannot be excluded. The risk of local effects is therefore adequately controlled.
Dermal, local effect / acute		
Eyes, local effect		



## 4. Guidance to DU to evaluate whether he works inside the boundaries set by the ES

### 4.1 Environmental emissions (Contributing scenario 1)

A user is consistent with this ES if, either:

- A) The proposed risk management measures, and conditions of use, as described above are met, or  
 B) The downstream user can demonstrate that their operational conditions and implemented risk management measures are adequate, by reference to one or more of the following:

- 1) Where relevant measured ambient data in the receiving environment (obtained in accordance to the REACH guidance on monitoring data) demonstrate exposures below the following PNEC concentrations:  
 PNEC<sub>freshwater</sub>: 0.04 µg Ag/L (Soluble Ag)  
 PNEC<sub>marine</sub>: 0.86 µg Ag/L (Soluble Ag)  
 PNEC<sub>sediment freshwater</sub>: 438 mg Ag/kg dwt  
 PNEC<sub>sediment marine</sub>: 438 mg Ag/kg dwt  
 PNEC<sub>soil</sub>: 1.24 mg Ag/kg ww  
 PNEC<sub>STP</sub>: 0.025 mg Ag/L (Soluble Ag)

- 2) In the event the user has measured data available but not exactly those required as per REACH guidance, the user can still compare effluent concentrations with the following default emissions calculated for the default ES described above:

Concentration in waste water released to freshwater STP must be < 6.67 µg Ag/L (soluble silver) to ensure that the risk characterisation ratio does not exceed 1.

Concentration in waste water released to marine water must be < 86 µg Ag/L (soluble silver) to ensure that the risk characterisation ratio does not exceed 1.

The user may make use of an appropriate scaling tool such as MetalEUSES (free download: <http://www.arche-consulting.be/Metal-CSA-toolbox/duscaling-tool>) to estimate the associated exposure for other parameters than the default ones included here above to demonstrate safe use under this specific scenario or situation.

- 3) In case **no safe use can be demonstrated under 1 or 2 above** based on monitoring data, but the downstream user has knowledge on emitted annual or daily loads, he can compare its emission to water to the emission ratio listed below:

The RCR will be equal to or lower than those stated above if they emit less than 0.0133 kg Ag/day to on site or off site wastewater treatment works (equivalent to 0.0025 kg Ag/day to the receiving water).

- 4) In case the user does not have emission or ambient measured info he can use the Metal EUSES scaling tool (free download: <http://www.arche-consulting.be/Metal-CSA-toolbox/duscaling-tool>) to estimate the associated exposure for other parameters than those included here above to demonstrate safe use under this specific scenario or situation.

### 4.2 – 4.3 Occupational exposure (Contributing scenarios 2 - 3)

The downstream user (DU) works inside the boundaries set by the ES if the proposed operational conditions (OCs) and risk management measures (RMMs) as described in the exposure scenario (ES) are met (including substance/product characteristics). If the DU's conditions slightly deviate (such deviations are specified below) from the conditions as described in the ES, the DU may either inform the supplier of the substance to reflect the DU's conditions in a modified exposure scenario or has to ensure his slightly modified OCs and implemented RMMs are adequate. Depending on the basis for the exposure assessment (EA) conducted for the ES, this needs to be done in different ways:

Use of measured data as basis for assessment: If the EA in the ES is based on measured data, the same approach can be used at DU level. Please note that 6 measurements per workplace are required for an EA as a minimum. Depending on the variability of the data sets (expressed as the geometric standard deviation) and the level of the resulting risk characterisation ratio (RCR), additional measurements may be required. Only measurements of personal exposure of the inhalable fraction of airborne dust (according to EN 481) should be used. The exposure data shall either be applicable to the length of a specific task to be assessed or to a full-shift (i.e. sampled over a duration of at least 120 min) if the task to be assessed is conducted for a significant portion of the work shift. From the exposure data set the 90th percentile is to be used as a reasonable worst case (RWC) estimate for comparison with the relevant DNEL. RPE may be taken into account by applying the assigned protection factor applicable to the equipment used as given in EN 529:2005.

It is noted that deviations from the ES are only allowed for the efficacy of installed RMMs (but not the type of RMM), exposure duration and personal protective equipment used. However, due to the acute local (corrosive) effects of silver nitrate, exposure duration should not be used as a risk management measure when assessing exposure using MEASE.

Use of exposure models: If the EA in the ES is based on modelled data, the same model can be used to justify specific slight deviations from the conditions as described. All parameters needed to run the exposure estimation tool MEASE (available on [www.ebrc.de/mease.html](http://www.ebrc.de/mease.html)) can be found in the ES. It is noted that the installation of the described RMMs is mandatory and that exclusively the modification of the used PPE is allowed as deviation. The only parameters which may therefore be modified in the MEASE-calculation are consequently exposure duration, efficacy of the installed RMMs and PPE.

Generic to both assessment bases: Safe use is demonstrated, if the calculated exposure level is below the relevant DNEL (RCR <1). It is noted that smaller RCRs provide additional margin of safety and should therefore be envisaged.

DNEL<sub>inhalation</sub>: 0.016 mg/m<sup>3</sup> (as silver nitrate)